



# eInvoice-Viewer 1.0.0

User Documentation

---

# INHALTSVERZEICHNIS

|                         |   |
|-------------------------|---|
| Quick Setup             | 3 |
| Install                 | 3 |
| Upload and Activate     | 4 |
| Upload                  | 4 |
| Activate                | 4 |
| Setup your Post or Page | 5 |
| Settings                | 6 |

# QUICK SETUP

## INSTALL


- Upload and Activate the „WordPress – elInvoice-Viewer“ Plugin
- Add the shortcode **[einvoice\_viewer]** to a page or post.
- Ready

# UPLOAD AND ACTIVATE

## UPLOAD

After you downloaded and saved the 'WordPress - eInvoice-Viewer' Plugin you have to upload it to your Wordpress installation.


Please go to you 'Plugins/Add New' Menu, select 'Upload' from the top links and choose the downloaded ZIP-File at the upload-field.



Add Plugins [Upload Plugin](#)

After selecting the File please press the „Install Now“ Button.

If you have a plugin in a .zip format, you may install or update it by uploading it here.



Datei auswählen

sp-einvoi...-viewer.zip

[Install Now](#)

## ACTIVATE

After the Plugin is uploaded you will get a success screen.


Please use the link „Activate Plugin“ to activate the Plugin.

# SETUP YOUR POST OR PAGE

To integrate the 'WordPress - eInvoice-Viewer' to your site you have to add a simple shortcode to the needed page or post.

**[einvoice\_viewer]**

After you saved the page or post, there will be a Upload Section at the frontend to upload a XRechnung, ZUGFeRD, FACTUR-X or UBL XML.



Remaining uploads today: 9


☐ Show BT numbers

To check the "Show BT numbers" checkbox by default use the following shortcode

**[einvoice\_viewer bt="1"]**

# SETTINGS

At the WordPress backend there is a now entry at the Settings block to adjust the settings for the 'WordPress - eInvoice-Viewer'.



## E-Invoice Viewer

### E-Invoice Viewer

Add the [einvoice\_viewer] shortcode to a page to let visitors upload and visualize an electronic invoice.

Daily uploads per visitor

Per calendar day. Logged-in users are counted by user, anonymous users by IP address. 0 = unlimited.

Maximum file size ( MB )

Trust proxy header

☐ Use the X-Forwarded-For header for the client IP ( only enable behind a trusted reverse proxy ).

Show BT numbers by default

☐ Display the EN16931 Business Term ( BT ) numbers next to the fields. Visitors can still toggle this in the viewer.

The “**Daily uploads per visitor**” setting allows you to specify the daily number of uploads per visitor.

The “**Maximum file size**” determines the maximum size of a file that can be uploaded. Please also be aware of any limits set by your web hosting provider.